2024-02-08, v4.3.1.501
BnfMaker.exe
1. #30427 Add phonetic Pronas to the StandardKeyword.txt file

2023-09-18, v4.3.0.504
_vxt_configuration.jcd & jcf
1. #30051 New parameter Microphone.AudioSource
   Values: "DEFAULT"; "VOICE_COMMUNICATION"; "VOICE_RECOGNITION"; "VOICE_CALL";
   Default value: "VOICE_COMMUNICATION"

2023-04-28, v4.3.0.501
_vxt_configuration.jcd & jcf
1. #25463 New parameter AsrTuning.Dcc
2. #25940 New parameters TtsTuning.TtsRateMin & TtsRateMax

2023-01-11, v4.2.9.504
_vxt_packageInfo.jcf
1. #23734 Fix Name parameter in _vxt_packageInfo (HR - ID - LV - RI - SA - SL - TW)

2022-11-18, v4.2.9.502
_vxt_configuration.jcd & jcf
1. #22491 New parameter Microphone.ScoConnectionDelay

2022-08-31, v4.2.9.501
_vxt_rules.txt
1. Special regex rules applied to all languages

2022-03-09, v4.2.8.501
_vxt_rules.txt
1. Special regex rule: avoid " , "

BnfMaker.exe
1. New suffix grammar
2. Added the version information in the properties of the exe

2022-02-28, v4.2.8.500
_vxt_configuration.jcd
1. #1089 New value in Calibrate.AsrType -> Q (SUFFIX)
/Tools/Schema_jcd/hcm
1. Location for HCM config files

2021-12-14, v4.2.7.503
_vxt_rules.txt
    1. #1850 Special regex rules

2021-10-15, v4.2.7.503
_vxt_configuration.jcd
    1. ReliabilityLevel default value changed from 4000 to 5000

_vxt_configuration.jcf
    1. ReliabilityLevel changed from 4000 to 5000 in the following languages: EN - ES - FR - FL - GE - PL

2021-05-26, v6.1.2.517
_vxt_configuration.jcd
    1. #1665 New parameter added Calibrate.DisplayLanguage

_clb_labels.dat
    1. #1665 New file of messages to be displayed on the screen

2021-02-18, v4.2.5.510
Latvian language
    1. The folder LV is moved from "Phonetic Languages" folder to "Languages" folder

2021-01-19, v4.2.5.509
_vxt_calibratelist.txt
    1. #1497 Suppress the values with only 1 digit. Include values with 2 or 3 digits. Set the ASRType value to H (Hundreds) -> Applied only to FR-EN-ES languages

2020-12-15, v4.2.5.506
_vxt_configuration.jcd
    1. #1687 New parameter added Microphone.Bluetooth.NFCOffAfterConnect

_vxt_calibratelist.txt
    1. #1497 Adapt _vxt_calibratelist.txt for every language adding the "ROUND" value to the array.

```
2020-05-14, v6.1.2.509
 _vxt_configuration.jcd
    1. Calibrate.AsrType, LIST added to enum values (Calibrate will use the AsrType
from the _vxt_calibratelist.txt file)
    2. New parameter added Calibrate.AutoResetTimeout

 _vxt_calibratelist.txt
    1. Added a new value to the array (ROUND). Round 1 is always the first thing
Calibrate will say to the user. If the user said it correctly, we continue to Round
2. In case there is no Round 2 configured, 0 will always be used.
```

```
2020-03-31, v4.2.5.502
 _vxt_configuration.jcd
    1. Bluetooth.AudioMode, MODE_NATIVE added to enum values
    2. Input.RecordSound new value "2" added to record only calibrate input sounds
```

```
2020-02-12, v4.2.5.500
 _vxt_configuration.jcd
    1. Bluetooth.AbortSpeechWhenLost, Bluetooth.ScoReconnectTime,
Bluetooth.ReconnectText and Bluetooth.AudioMode added
```

```
2019-09-13, v4.2.4
 _vxt_configuration.jcd
    1. Calibrate.AsrType, K (Kilos) added to enum values
    2. Microphone.Mode default value changed from WIRED to OPEN
```

```
2019-05-17, v4.2.2
    1. Fixed: RI language - renamed _vxt_asr_it.dat file to _vxt_asr_ri.dat
```