

2024-02-08, v4.3.1.501

BnfMaker.exe

1. #30427 Add phonetic Pronas to the StandardKeyword.txt file

2023-09-18, v4.3.0.504

_vxt_configuration.jcd & jcf

1. #30051 New parameter Microphone.AudioSource
Values: "DEFAULT"; "VOICE_COMMUNICATION"; "VOICE_RECOGNITION"; "VOICE_CALL";
Default value: "VOICE_COMMUNICATION"

2023-04-28, v4.3.0.501

_vxt_configuration.jcd & jcf

1. #25463 New parameter AsrTuning.Dcc
2. #25940 New parameters TtsTuning.TtsRateMin & TtsRateMax

2023-01-11, v4.2.9.504

_vxt_packageInfo.jcf

1. #23734 Fix Name parameter in *_vxt_packageInfo* (HR - ID - LV - RI - SA - SL - TW)

2022-11-18, v4.2.9.502

_vxt_configuration.jcd & jcf

1. #22491 New parameter Microphone.ScoConnectionDelay

2022-08-31, v4.2.9.501

_vxt_rules.txt

1. Special regex rules applied to all languages

2022-03-09, v4.2.8.501

_vxt_rules.txt

1. Special regex rule: avoid " , "

BnfMaker.exe

1. New suffix grammar
2. Added the version information in the properties of the exe

2022-02-28, v4.2.8.500

_vxt_configuration.jcd

1. #1089 New value in Calibrate.AsrType -> Q (SUFFIX)

/Tools/Schema_jcd/hcm

1. Location for HCM config files

2021-12-14, v4.2.7.503

`_vxt_rules.txt`

1. #1850 Special regex rules

2021-10-15, v4.2.7.503

`_vxt_configuration.jcd`

1. ReliabilityLevel default value changed from 4000 to 5000

`_vxt_configuration.jcf`

1. ReliabilityLevel changed from 4000 to 5000 in the following languages: EN - ES - FR - FL - GE - PL

2021-05-26, v6.1.2.517

`_vxt_configuration.jcd`

1. #1665 New parameter added Calibrate.DisplayLanguage

`_clb_labels.dat`

1. #1665 New file of messages to be displayed on the screen

2021-02-18, v4.2.5.510

Latvian language

1. The folder LV is moved from "Phonetic Languages" folder to "Languages" folder

2021-01-19, v4.2.5.509

`_vxt_calibratelist.txt`

1. #1497 Suppress the values with only 1 digit. Include values with 2 or 3 digits. Set the ASRType value to H (Hundreds) -> Applied only to FR-EN-ES languages

2020-12-15, v4.2.5.506

`_vxt_configuration.jcd`

1. #1687 New parameter added Microphone.Bluetooth.NFCOffAfterConnect

`_vxt_calibratelist.txt`

1. #1497 Adapt `_vxt_calibratelist.txt` for every language adding the "ROUND" value to the array.

2020-05-14, v6.1.2.509

_vxt_configuration.jcd

1. Calibrate.AsrType, LIST added to enum values (Calibrate will use the AsrType from the *_vxt_calibratelist.txt* file)
2. New parameter added Calibrate.AutoResetTimeout

_vxt_calibratelist.txt

1. Added a new value to the array (ROUND). Round 1 is always the first thing Calibrate will say to the user. If the user said it correctly, we continue to Round 2.
2. In case there is no Round 2 configured, 0 will always be used.

2020-03-31, v4.2.5.502

_vxt_configuration.jcd

1. Bluetooth.AudioMode, MODE_NATIVE added to enum values
2. Input.RecordSound new value "2" added to record only calibrate input sounds

2020-02-12, v4.2.5.500

_vxt_configuration.jcd

1. Bluetooth.AbortSpeechWhenLost, Bluetooth.ScoReconnectTime, Bluetooth.ReconnectText and Bluetooth.AudioMode added

2019-09-13, v4.2.4

_vxt_configuration.jcd

1. Calibrate.AsrType, K (Kilos) added to enum values
2. Microphone.Mode default value changed from WIRED to OPEN

2019-05-17, v4.2.2

1. Fixed: RI language - renamed *_vxt_asr_it.dat* file to *_vxt_asr_ri.dat*