



QUICK INSTALLATION GUIDE

VOIXTREME ESSENTIALS EDITION

This document will guide you through the basic installation process, for your new VoiXtreme apk and its plugins included in this package.

Here you are going to find: VoiXtreme_Engine.apk and VoiXtreme_Calibrate.apk, a complete guide for install and configure the product. And a complete source of archives, for customize the interface of the VoiXtreme.





VOS DÉFIS SONT
NOS INNOVATIONS

Hub One S.A.

Continental Square, 1 2 Place de Londres, Bât. Mercure
93290 TREMBLAY EN FRANCE
FRANCE

hubone.fr

Une filiale du **Groupe ADP**

Table of Contents

PREVIOUS STEPS	4
CONNECTING THE DEVICE TO THE COMPUTER	6
INSTALLING VOIXTREME ON THE DEVICE	7
PRE-REQUISITES	7
AUTOMATIC INSTALLATION	7
MANUAL INSTALLATION	9



Congratulations for purchasing your new VoiXtreme®!

This guide will show you in a few easy steps, how to install a fully operational product on your terminals. For quickly begin improving the productivity of your business.

- Thanks for trusting VoiXtreme. For us, your business comes first!

NECESSARY MATERIAL:


1. Windows computer



2. An AndroidTerminal



3. Usb wire



3. VoiXtreme Installation package




PREVIOUS STEPS

The first thing you need to do is copy the VoiXtreme® package on your computer and execute it.

After that, you should have the VoiXtreme® folder named as the version provided of VoiXtreme® (VXXX). The default path where the files are copied is:

C:\HubOne\MobileDevices\VoixNext\VXXX. This folder contains the following files and folders:

- (1) the installation apk for VoiXtreme® and its plugins into the Devices folder
- (2) the configuration manuals into the Help folder
- (3) a Languages folder with multiple subfolders containing each language available for VoiXtreme®
- (4) a Tools folder with some extra resources.



Additionally, you will be provided with the Visual Json Editor application. This program can help you to modify easily the configuration files of VoiXtreme®.


Execute the exe file corresponding to this program and install it in your PC. It will be installed in C:\HubOne\VisualJsonEditor.

For further information about how to configure your VoiXtreme® app, refer to:
[*VoiXtreme_quick_configuration_guide*](#)

CONNECTING THE DEVICE TO THE COMPUTER



Once the resources are on your computer, it's time to add the required files on the devices to start working with the VoiXtreme® app. For now, we only need to install the VoiXtreme® apps and the resource directory named VoiXtreme®.

Now connect the device to the computer with the usb wire.



Install the drivers that your computer requires if it's the first time you connect the device. Usually that is an automatic process. If you have any problem with this step refer to the technical support of the device.

For the correct working of the file-transference process, be sure that the connection mode on your device is: Connected as media device (MTP) and the USB debugging is enabled (Settings – Developer Options – USB Debugging)



If your device is in another different mode, change it by clicking the connected mode label on the scrollable menu of the android status bar.

INSTALLING VOIXTREME ON THE DEVICE

Now that your Android device is connected, you have access to its file system through your Windows file explorer.

Included in the VoiXtreme® installation package, you will find the apks files necessary to install the application in your Android device. Nevertheless, we provide you a bat file to perform an automatic installation.

PRE-REQUISITES


```
Pending connection from an Android terminal to the pc...
```

To perform a successful installation of VoiXtreme®, it is convenient to:


- Check if “adb” folder is present in “Tools” folder of the installation package provided
- Connect only **ONE** device through the USB port of your PC
- Allow USB debugging in your Android device (Settings - Developer Options -Debugging – USB Debugging)

AUTOMATIC INSTALLATION

From “C:\HubOne\MobileDevices\VoixNext\Vxxx\Languages” folder, look for your desired language to install and execute “Install_VoiXtreme.bat”.



In each “language” folder, you will find one bat file:



- **Install_VoiXtreme.bat:** This file calls a generic bat file located in TOOLS folder (_Install_VoiXtreme.bat). It installs the VoiXtreme apps into the device: VoiXtreme Engine and VoiXtreme Calibrate. The app VoiXtreme Demo Picking could be installed too.

Before performing installation, if the folder “voixtreme”, that contains configuration files, exists in your Android device, you will be required to delete or add the corresponding files for the language you selected to that voixtreme existing folder. If this folder does not exist in the device, it is created for the first time.

Once the installation is finished, VoiXtreme Calibrating app is launched on your Android device and it is ready to use.

The Demo Picking app renames the different language files for executing this app selecting the languages.

NOTE:

- *If some file is missing, the program will not work! Pay special attention if you change something of the configuration files, because every file must be in its place!*
- *If you use a Bluetooth headset, you need to install the BT Pairing app manually. Just copy the corresponding apk file in your device and install it. Then, open it once to grant all the permissions required*

MANUAL INSTALLATION

Alternatively, you can manually perform the VoiXtreme® installation.

That is, copy the “voixtreme” folder from your desired language installation into your device internal storage directory.

Then copy APK files located in

C:\HubOne\MobileDevices\VoixNext\Vxxx\Devices\GENERIC_ANDROID into your device internal storage through your Windows file explorer.

Now on your Android device, you need a file browser to open the apk location. If the terminal didn't have a reliable one, we recommend you ASTRO file browser:


play.google.com/store/apps/com.metago.astro

Have in mind that the path which appears in your Android file browser could be different from the path you put your files in the Windows file browser.

If you were unable to find the internal storage path, try with the emulated path (/storage/emulated/0)

Once in the internal storage root directory, just execute all apk files you copied there. Now accept the permissions by clicking on **Next** button, and install the applications by clicking on **Install** button. Open them once installed to grant all the permissions required.

And that's all! Enjoy your new VoiXtreme®!



Once the VoiXtreme® apps are installed, when you launch VoiXtreme Calibrate app for the first time, the specific language obb file (**main.1.com.voixtreme.vocalengine.obb**) will be automatically copied from “voixtreme” folder into the application folder “Internal storage\Android\obb\com.voixtreme.vocalengine”

You can launch Calibrate app and automatically the VoiXtreme engine will be started or use this component with a TellNext profile.